

Your SONY READER and eBooks

What you'll need:

- Baxter County Library Card
- Computer: Windows or Mac with Internet Connection
- Sony Reader
- Free Software
 - o Adobe Digital Editions – and an Adobe ID
 - o Adobe Flash
 - o Sony eBook Library software

1. Setting up your Computer

1. Go to the Baxter County Library website www.baxlib.org.
2. Click on the Library2Go logo
3. On the Library2Go page, look on the left-hand side for Digital Software, click on Adobe Digital Editions.
4. Download and install Adobe Digital Editions. This software requires Adobe Flash.
5. Open up Adobe Digital Editions. It will ask you to activate your software with an Adobe ID. We recommend you create an Adobe ID.
6. When you create an Adobe ID:
 - a. You may download the eBook to more than one computer as long as the computers all use the same Adobe ID. (Up to 6 computers can be activated using one Adobe ID)
 - b. You can transfer your eBooks only to **Sony Readers** that are using the same Adobe ID.
7. If you decide to continue anonymously:
 - a. **You will not be able to transfer eBooks to your Sony Reader!**
 - b. You may only download to one computer.
 - c. You can activate an Adobe ID at any time. However, you may lose the rights to see any eBooks that were downloaded previously.
8. Follow the steps to create an Adobe ID.




2. Checkout an eBook & download to your Computer

1. Go back to the Library2Go homepage.
2. Search for eBooks. You can limit your search to eBooks and to the type of eBooks your device can read by clicking on the down arrow on the box located under the search box. **The Sony Reader can read both the EPUB & PDF formats.**
3. You can limit your search to show only available eBooks.
4. If you do not limit the format, the eBooks will be mixed with audio books. You can tell the difference by checking the type of book and what they will play on.
5. To check out a book, click **Add to download cart**. If you are *ready* to check out click on **Proceed to Checkout**.
6. Select Baxter County Library from the drop down menu of libraries. Login using your 14 digit Library barcode number. Click on **Confirm checkout**. You can have up to 3 titles checked out at any given time.
7. Click on **Download**. Open with Adobe Digital Editions.

3. Transferring an eBook to your Sony Reader

1. Install eBook Reader Library by Sony software to your computer or laptop from <http://www.ebookstore.sony.com/download/>.
2. Before connecting the **Sony Reader** to your computer, turn it on and let it boot up.
3. Activate your **Sony Reader** by plugging it into your computer with Adobe Digital Editions open. Adobe Digital Editions will detect your **Sony Reader** and ask to activate it using the same Adobe ID as your copy of Adobe Digital Editions. Follow the prompts. (It may take a few minutes for Adobe Digital Editions to see your **Sony Reader**.)
4. Your **Sony Reader** will appear on the left under Bookshelves.
5. To transfer your eBook to the **Sony Reader**, click on your previously downloaded eBook and drag it to the **Sony Reader** icon. The eBook will transfer.



6. Disconnect your **Reader** by finding the icon on the right side of your taskbar (at the bottom of your PC screen) that says "Safely remove hardware." It is a gray rectangle with a green arrow above it, pointing left. When you click it, you should see the words "Safely remove ..." and a reference to the drive letter your **Sony Reader** is using.
7. To find your new eBook on your **Sony Reader**, go to Books. Enjoy!

4. How to return items early

1. To return an eBook early so that you may check out another eBook, hover your mouse over the book in Adobe Digital Editions.
2. Click on the **Item Options** arrow.
3. Click on **Return Borrowed Item**.

5. When your eBook expires

1. When your license to view the eBook expires, you will not be able to read it any longer. However, the data for the eBook will stay on your computer and **Sony Reader** until you delete it.
2. To delete from Adobe Digital Editions, click on the **Item Options** arrow over the eBook title.
3. Click **Delete Item**.

To delete from your **Sony Reader**, click on the **Sony Reader** icon in Adobe Digital Editions. Click on the **Item Options** arrow over each book and then click **Delete Item**. Or, with the eBook open to the "Protected Page" message, push Options on the **Sony Reader** scroll down until you see Delete Book.



Donald W. Reynolds
LIBRARY
Serving Baxter County
(870) 580-0987
300 Library Hill
Mountain Home, AR 72653